




TRAINING GUIDE

ArcGIS Server and Geodatabase Administration

Part 1



ArcGIS for Server and Geodatabase Administration - Part 1

Here at Lucy, we understand that our software is requiring more skills in ESRI technology and these Esri systems can be difficult to manage without training. In this workshop, we will explore the nature of ArcGIS for Server v10.3.1, touch on key principles and techniques, as well as explore best practices for integration into Lucy. We will cover some key administration best practices for: design, setup, maintenance, and optional editing workflow. Even though we won't be covering the full gamut of ESRI technologies, we will be focused on the administration of ArcGIS for Server, how this relates to the IT and GIS administrators and what are some basic principles for enabling ArcGIS for Server to be compatible with Lucy.


Table of Contents

Setup	2
ArcGIS for Server Design.....	2
ArcGIS for Server Setup.....	4
Connect to ArcGIS for Server from ArcCatalog	9
ArcGIS for Server and Extensions Patch Notification	11
Installing and Configuring ArcGIS for Server Web Adapter	12
SQL Server Specifications	15
SQL Instance Setup	16
Install SQL Server for ArcSDE for Workgroup.....	16
SQL Server Enterprise Setup	24
Enabling ArcSDE for Workgroup Databases	25
Install SQL Server Native Client	33
Connect and Create Geodatabase in Workgroup	33
Registering the Geodatabase in ArcGIS for Server	39
Create Enterprise Geodatabase (formerly ArcSDE)	43
Publishing and Configuring Map Services	44
Unlock Schema	48
Enabling the Geometry Service	51
Creating a Geocoding Service	52
Securing a Map Service	54
How to Create a Feature Service	60
Added GIS Functionality	60
Redlining	60
Publishing a Feature Service	67
Publishing an Offline Feature Service	71

Setup

ArcGIS for Server Design

- ArcGIS for Server 10.2 and higher is supported for Lucity
- Support Windows Server 2008 R2 or higher
 - For Virtualization, recommend Windows Server 2012 R2
- Server should have 2-4 cores minimum and 4GB of RAM per core. For a 4 core system, you should have at least 16GB of RAM.
- SQL Server 2008/2008R2 is no longer supported after 10.3.x. Recommend SQL Server 2014 if upgrading
- If you have virtual servers, make sure you dedicate resources and have the latest VMware or Hyper-V software available. Based on ESRI's testing, Virtual software is the key to many performance issues. Make sure in VMware environments that you subtract overhead of two cores for the Virtual Environment so ArcGIS for Server map services doesn't pool across the Virtual overhead cores. If you don't, you will see a significant performance decrease in ArcGIS for Server.
- Try to limit map services to utilize 4 pools per core maximum. Anything more than that, you could allow ArcGIS for Server crashes when many people are simultaneously hitting your server.
- If you have a dedicated system for ArcGIS for Server, try creating a RAID 1 SSD configuration for your hard drives. Also, use the latest version of SSD standards as this will increase performance and reliability. For all new SSD cards, it will take at least 40 years before they reach their read/write maximum. This benchmark test was performed on a 24/7 continuous read/write routine. If SAS drives, use RAID 10 with a good RAID controller.
- Space depends on caching. If you plan to cache imagery, please account for large image files. Remember, each scale in the cache will have separate tiles for each scale. If you have 9 scales within a cache, you will have nine separate tiles of cache. Smaller scale images will be smaller in size and the larger scale images will be larger in size.
- Suggest HTTP and HTTPS Secure Design when setting up ArcGIS for Server security Configuration
- If intranet only, use HTTP only unless otherwise specified by your IT administration
- For Lucity, we use ArcGIS Tokens for authentication mode. **Do not** use Web Tier
- Lucity Web, Lucity Services, Lucity Mobile Server servers need access to the map service rest endpoints in order to function. All devices need to be able to access the map services as well.




ArcGIS for Server Setup

1. First, run the upgrade utility on existing system. If this is a new system, bypass the utility. Remember, ArcGIS for Server needs to be 64bit but the web adaptor (optional) can be on either 32bit or 64bit.

Note: When installing ArcGIS for Server on a separate server than your SQL Server 2014 instance, you need the SQL Server Native Client 64 bit. SQL Server 2012 native client and previous versions of the native client will work as well (i.e. SQL Server 2012 or SQL Server 2008 R2 native clients). Latest SQL Server 2012 Native 64 bit Client download link: <http://www.microsoft.com/en-us/download/details.aspx?id=29065>

Files	Guides	File Size	Select
Uninstall ArcGIS software prior to ArcGIS 10.1	Read me	1.20 MB	Download
ArcGIS for Server	Install guide	814.63 MB	Download
ArcGIS Web Adaptor (IIS)	Install guide	22.31 MB	Download
ArcGIS Web Adaptor (Java Platform)	Install guide	16.93 MB	Download
ArcGIS Data Store for Server	Install guide	124.17 MB	Download
ArcGIS GeoEvent Extension for Server	Install guide	188.10 MB	Download
ArcGIS Data Interoperability for Server		511.67 MB	Download
ArcGIS Data Reviewer for Server	Install guide	56.33 MB	Download
ArcGIS Workflow Manager for Server	Install guide	20.92 MB	Download
ArcGIS Server Cloud Builder on Amazon Web Services (Windows)		57.86 MB	Download
Portal for ArcGIS	Install guide	789.35 MB	Download
ArcGIS License Manager (Windows)	Reference guide	20.26 MB	Download
ArcGIS License Manager (Linux)	Reference guide	109.92 MB	Download
ArcObjects SDK for the Microsoft .NET Framework		654.00 MB	Download
ArcObjects SDK for Java (Windows)		413.22 MB	Download
Python 2.7.8 (64-bit)		24.80 MB	Download


2. Download and start the install for ArcGIS for Server Windows
3. Once installation starts click next.




4. In the next dialog, click on 'I Accept' and click next.
5. In the 'Select Feature' dialog, click next and accept defaults. .NET Extension Support is only used for Lucity SOE.
6. For python, this is needed for geoprocessing and click next.
7. In the 'Specify ArcGIS for Server Account, create a username and passwords for arcgis. Recommend to add arcgis as a user within Active Directory and add this to ArcGIS for Server Account information <domain>\<user>.




8. In the next screen, you will be given the option to export your configuration; this is recommended and will be helpful during upgrades. Click next and install.



9. When finished, you will need to activate. Refer to Enabling ArcSDE for Workgroup Databases section for more detail about the activation process.
10. When finished activation, you will be prompted to create a new site.




11. Click on create a new site and supply the username and password for the site administrator account. Click next.



The screenshot shows the 'ArcGIS Server Manager' window with a modal dialog titled 'Primary Site Administrator Account'. The dialog contains the following text: 'Create the account that will be the primary administrator for this ArcGIS Server site. This is a new account that is stored with the site and is not an operating system account. You will use this account when logging in to Manager.' Below this text are three input fields: 'Username:' with the value 'AGS', 'Password:' with masked characters, and 'Confirm Password:' with masked characters. At the bottom right of the dialog are 'Back' and 'Next' buttons.

12. Specify the root server directory and configuration storage. Your server configuration is stored in the config-store directory and your working directories are stored in directories (arcgiscache, arcgisjobs, arcgisoutput, arcgissystem). In this example we will take the defaults.



The screenshot shows the 'ArcGIS Server Manager' window with a modal dialog titled 'Specify Root Server Directory and Configuration Store'. The dialog contains the following text: 'When you create an ArcGIS Server site, several directories are installed to store output images, geoprocessing job results, cached images, and more. You can choose this location, but it must be accessible from each machine in your site.' Below this text are two input fields: 'Root Server Directory:' with the value 'C:\arcgisservice\directories' and 'Configuration Store:' with the value 'C:\arcgisservice\config-store'. At the bottom right of the dialog are 'Back' and 'Next' buttons.


13. Click next and finish when done.

ArcGIS for Server does not need a web client to run. ESRI chose to use Tomcat as the servlet engine for ArcGIS for Server and can be a stand-alone system if used internally. However, if you want to serve webpages out through IIS, consider installing a Web Adapter. ArcGIS for Server web adapter will act as a proxy server that will pass requests to and from ArcGIS for Server. Web Adapter will also be able to create an alias URL location for your ArcGIS for Server. ArcGIS for Server by itself needs to have port 6080 as the rest service endpoint for the URL. For example: `http://<internalservername>:6080/arcgis/rest/services` is the URL without the Web Adapter. When using the Web Adapter, requests can be masked through an alias URL designation `http://<URLname>/<virtualdirectory>/rest/services`. The Web Adapter takes care of the requests to and from ArcGIS for Server using port 6080 and translating this to the user. The Web Adapter for ArcGIS for Server can be located on ArcGIS for Server machine running IIS or on a different server within the LAN or a DMZ. For internet and intranet based ArcGIS for Server services, it's recommended to use a DMZ with the firewall open from DMZ web server to the internal ArcGIS for Server on port 6443. The Web Adapter will be installed on the DMZ web server and using ArcGIS for Server installation media. Also, it is highly recommended that the Web Adapter uses HTTPS as the protocol within a secure design as well as running ArcGIS for Server as HTTPS and HTTP. In ArcGIS for Server design section, we have added a diagram of what this actually looks like.


Notes: _____

Connect to ArcGIS for Server from ArcCatalog

1. Open ArcCatalog and go to the TOC. Expand GIS Servers.



2. Click on Add ArcGIS for Server and choose Administer GIS Server. As a note, you can add users to be able to publish gis services without having administrative rights.



3. In the general dialog, you need to add the URL and the username and password for administrating the server. Make sure you use the exact case for your username and password as ArcGIS for Server is now case sensitive. If Web Adapter is installed, you can use the Web Adapter URL to connect to ArcGIS for Server if it is setup to accept management.

The screenshot shows the 'General' dialog box for configuring ArcGIS for Server. The 'Server URL' field contains 'http://lukesavage:6080/arcgis'. Below it, the 'ArcGIS Server' URL is 'http://myserver:6080/arcgis' and the 'Spatial Data Server' URL is 'http://myserver:8080/arcgis'. The 'Server Type' is set to 'ArcGIS Server'. The 'Staging Folder' is 'C:\Users\savage\AppData\Local\Temp\arc1CC5\Staging'. There is a checkbox for 'Use ArcGIS Desktop's staging folder' which is checked. The 'Authentication' section has a 'User Name' field with 'AGS' and a 'Password' field with masked characters. There is a checkbox for 'Save Username/Password' which is checked. At the bottom, there are links for 'About ArcGIS Server connections' and 'About Spatial Data Server connections'. The 'Finish' button is highlighted.

General

Server URL: vices

ArcGIS Server:
Spatial Data Server:

Server Type:

Staging Folder:

☒ Use ArcGIS Desktop's staging folder

Authentication

User Name:

Password:

☒ Save Username/Password

[About ArcGIS Server connections](#)
[About Spatial Data Server connections](#)



< Back Finish Cancel

4. Click finish.

Notes: _____

ArcGIS for Server and Extensions Patch Notification

Go to the Start Menu/All Programs/ArcGIS app folder and choose Check for Updates to check for ArcGIS for Server patches



Notes: _____


Installing and Configuring ArcGIS for Server Web Adapter

1. Download the ArcGIS Web Adapter (IIS) and install.


Files	Guides	File Size	Select
Uninstall ArcGIS software prior to ArcGIS 10.1	Read me	1.20 MB	Download
ArcGIS for Server	Install guide	814.63 MB	Download
ArcGIS Web Adaptor (IIS)	Install guide	22.31 MB	Download
ArcGIS Web Adaptor (Java Platform)	Install guide	16.93 MB	Download
ArcGIS Data Store for Server	Install guide	124.17 MB	Download
ArcGIS GeoEvent Extension for Server	Install guide	188.10 MB	Download
ArcGIS Data Interoperability for Server		511.67 MB	Download
ArcGIS Data Reviewer for Server	Install guide	56.33 MB	Download
ArcGIS Workflow Manager for Server	Install guide	20.92 MB	Download
ArcGIS Server Cloud Builder on Amazon Web Services (Windows)		57.86 MB	Download
Portal for ArcGIS	Install guide	789.35 MB	Download
ArcGIS License Manager (Windows)	Reference guide	20.26 MB	Download
ArcGIS License Manager (Linux)	Reference guide	109.92 MB	Download
ArcObjects SDK for the Microsoft .NET Framework		654.00 MB	Download
ArcObjects SDK for Java (Windows)		413.22 MB	Download
Python 2.7.8 (64-bit)		24.80 MB	Download

Notes: _____

2. If you are using SOE, you need to enable the .net cross-domain policy files.



3. In the new Virtual Directory section, create your own virtual directory that will be used to alias ArcGIS for Server URL location. In this example, the URL change will be <http://<URLname>/RockStar/rest/services>. Click next.



4. Click Install.

5. After install is finished, you will be rerouted to a site that will allow you to configure your ArcGIS Web Adaptor. There are many options but the great thing about the Web Adaptor is you can be security conscience. Make sure you figure out if you want management internal only or allow management from both the Web Adaptor and ArcGIS for Server. Enabling administrative access to your site through the web adaptor is fine but discuss this option with your network engineer before enabling it to make sure the vulnerability is acceptable.

[Help](#) | [About](#)

 **ArcGIS Web Adaptor**

Which product do you want to configure with your Web Adaptor?


☒ ArcGIS for Server

☐ Portal for ArcGIS

 A GIS server is not configured with your Web Adaptor.
A portal is not configured with your Web Adaptor.

[Next >](#)

[Help](#) | [About](#)

 **ArcGIS Web Adaptor**

To configure the Web Adaptor, specify the URL and an administrator account for your GIS server.

FQDN →

GIS Server URL: ?
Example: http://gisserver.domain.com:6080

Administrator Username: ?


Administrator Password: ?

☐ Enable administrative access to your site through the Web Adaptor. ?

Only if it is internal. Don't recommend outside administrative access.

The following GIS servers are configured with your Web Adaptor:

- ACTWEB.TEST.LOCAL

 Last updated on 8/25/2015 10:13:20 AM

Use the following URL to access the Services Directory:
<http://actweb/rockstar/rest/services>

[< Back](#) [Configure](#)

6. Once configured, you should see a change in the green section of the web adaptor page.

SQL Server Specifications


- Server should have 2-4 cores minimum and 4GB of RAM so that SQL Server can use at least 2GB dedicated for the instance (sql server express can only use up to 1GB RAM per instance). For a Lucity and an Enterprise Geodatabase SQL Instance configuration, I would suggest 4 cores minimum with at least 8GB dedicated to SQL Server of RAM. Training, Development or Test servers can have less; 2 cores with at least 4GB of RAM which 1GB is dedicated to the SQL Server instance.
- RAID 10 configurations has become a standard RAID best practice. Please don't use onboard RAID controllers as they are not performance based.
- Don't load ArcGIS for Server on a database server. ArcGIS for Server is a memory hog and will fight for computer resources.
- Plan for data scalability 5 years out. If you have imagery that consumes 20GB and you know you will acquire a new image at least once within the 5 years, scale out four times the consumption rate. Space is cheap and there is no need to be caught in a low memory situation. Remember, digital imagery space is higher as they have a smaller focal length per image. If you acquired analog images in the past, digital images can be 2-3 times the memory size.
 - **Case study:** *Pocatello used 70GB 2012 Aerial for storage space. In their 2015 Aerial delivery, the database grew by 400GB. Higher resolution is becoming cheaper to purchase.*
- If in a virtual environment, make sure you have enough RAM and storage space for your servers. You could have as much as three to four servers minimum depending on your system design.

Notes: _____


SQL Instance Setup

Install SQL Server for ArcSDE for Workgroup


1. You can install from ArcGIS for Server disk or you can download installation from Microsoft for SQL Server 2012 Express 64bit with Advanced Services.
2. Click on the SQL Server executable.




3. Click on new sql server stand-alone installation or add features to an existing installation. In this example, we will be using a fresh installation.
4. You can assign different locations for your shared feature directory, most of the time you'll take the defaults and click next. If you don't want reporting services, uncheck the 'Reporting Services - Native' checkbox. If you don't know and may in the future, you can continue with it checked.




5. You can assign different instance names, install as a default instance, and create reporting services directory but in this particular example, we will use the defaults.



6. In this next dialog, turn on the sql browser to automatic startup



7. For Server Configuration, it is good to enable mixed mode. This is the case where you have an administrator and you would like to have SA as an admin user that is constant. Windows authentication only is bad if the person that administrates ever leaves and you disable their active directory account by accident. It's not the end of the world, but this is an IT assurance issue. For me, it's better to be safe than sorry. Store your SA password in a safe location that can be accessed in case of administrative role changes. Again, vulnerability and stability assurance measures are the key to a healthy working server environment. Reduce the number of server admins so you have a single point of entry into the database as an administrator. For those using AD domain or LDAP, please change the account name to include a domain user so you can browse the local server when added in a domain. SQL Server Browser, SQL Server Agent and the database engine is necessary to change to be network aware if using backup maintenance plans (database maintenance plans are enabled for SQL Server Standard, Developer or Enterprise only).



Notes: _____


8. On the data directories tab, it is good to change the location for easy backup queries and administration. However, system tables will use the Microsoft default location within the root directory of the databases. I would not recommend enabling user instances on the user instance tab as well as filestreaming unless you plan on loading large documents outside of the Geodatabase as blobs. Click next when complete.

The screenshot shows the 'Data Directories' tab in the SQL Server 2012 Setup wizard. The 'System database directory' is highlighted with a red arrow pointing to 'C:\data\MSSQL11.SQLEXPRESS\MSSQL\Data'. Other directories include 'Data root directory' (C:\data), 'User database directory' (C:\data\), 'User database log directory' (C:\data\log), 'Temp DB directory' (C:\data\temp), 'Temp DB log directory' (C:\data\temp\log), and 'Backup directory' (C:\backup).


9. Optional: In the reporting services configuration, if you are using the reporting services, install and configure. If not, I would install and not configure. I chose to install but not configure right away. If you chose not to install at all during the setup process, you will not see this dialog. Click next.

The screenshot shows the 'Reporting Services Configuration' dialog in the SQL Server 2012 Setup wizard. The 'Install only' option is selected under 'Reporting Services Native Mode'. The dialog also shows 'Reporting Services SharePoint Integrated Mode' with the 'Install only' option selected. The 'Next >' button is highlighted.

10. Your choice of sending Microsoft the error reports and usage automatically. I generally do this for a development or test environment. For a production environment, leave unchecked. Click Next.




11. If complete, you have successfully created a sql instance. If not, go through the troubleshooting information listed in the error log.
12. Go to start/all programs/Microsoft sql server 2012/sql server management studio. If you had sql server 2008 before, you can import profile settings.




13. Click connect

15. Right click the instance you connected to and choose properties




Notes: _____

16. Go to the memory tab and click on maximum server memory. You will want this to be a realistic number as the default puts an ungodly amount of maximum ram that will far exceed your server limit. Because we are treating this as a production server, you will want to dedicate resources to SQL Server. For the operating system, at least give the operating system 512 GB of RAM and for SQL Server adjust appropriately. In this case, I'm giving SQL Server 2 GB of RAM but it can be more depending on your instance load and available memory. All other defaults are fine.




17. Tab down to Processors in the TOC, I would highly recommend enabling 'Boost SQL Server Priority' on the server if other application like ArcGIS for Server are running on the same server. Otherwise, keep 'boost sql server priority' unchecked. **DO NOT ENABLE WINDOWS FIBERS (lightweight pooling)!** This is for older technologies and ArcSDE from v10 and higher uses XML calls to the SQL Server database so keep windows fibers disabled.



Notes: _____

18. Double the network packet size for the Geodatabase connections in the advanced menu item (from 4096 to 8192). For network traffic and performance, the Geodatabase network packets need the additional size increase.



SQL Server Enterprise Setup

Very similar to the workgroup setup above only that I recommend using default instance and locating all databases for Lucity and ArcGIS in one instance for ease of administration and resource dedication.

Enabling ArcSDE for Workgroup Databases

1. Download Database Server and install.


Select Downloads

Select the items below that you want to download:


Filter:

Files	Guides	File Size	Select
Uninstall ArcGIS software prior to ArcGIS 10.1	Read me	1.20 MB	Download
ArcGIS for Server	Install guide	814.63 MB	Download
ArcGIS Web Adaptor (IIS)	Install guide	22.31 MB	Download
ArcGIS Web Adaptor (Java Platform)	Install guide	16.93 MB	Download
ArcGIS Data Store for Server	Install guide	124.17 MB	Download
Database Server (Workgroup)	Install guide	143.57 MB	Download
ArcGIS GeoEvent Extension for Server	Install guide	188.10 MB	Download
ArcGIS Data Interoperability for Server		511.67 MB	Download
ArcGIS Data Reviewer for Server	Install guide	56.33 MB	Download
ArcGIS Workflow Manager for Server	Install guide	20.92 MB	Download


2. Click Next




3. Uncheck the checkbox next to Microsoft SQL Server Express Edition




4. Click next
5. Supply your instance name and windows login




6. If successful, click ok and move to step 24. If not, fix the connection issues.



7. The next section will authorize the SQL Server Express instance. For SQL Server enterprise, this is different as the subsequent topics will show you how to authorize Enterprise Geodatabases for SQL Server. Click next




8. The authorize option allows you to point to an authorize file supplied from ESRI or to authorize the software installation. In this example, we will be choosing the later. Click next




The image shows a 'Software Authorization Wizard' dialog box. At the top, the title bar reads 'Software Authorization Wizard' with a close button. Below the title bar, the section is titled 'Authorization Options' with a subtitle: 'You must authorize the software prior to use. Select from the options below.' The main area contains two radio button options under the heading 'Authorization Options':
1. A selected radio button (indicated by a blue dot) next to the text: 'I have installed my software and need to authorize it.'
2. An unselected radio button next to the text: 'I have received an authorization file from Esri and am now ready to finish the authorization process.'
Below the second option is a text input field and a 'Browse...' button. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'.

9. Again, you have the choice of email, website or through the internet. We will be performing the later. Click next.




10. The authorization information will need filled out. Click next. Click next.

11. In software authorization number dialog, you will need to supply the authorization number that ESRI has supplied to you for ArcGIS for Server Workgroup. Click next.



The image shows a 'Software Authorization Wizard' dialog box. The title bar reads 'Software Authorization Wizard' with a close button. The main content area has a header 'Software Authorization Number' followed by the instruction 'Enter the authorization number for your software product'. Below this, there is explanatory text: 'The authorization number consists of three letters and a series of numbers; similar to ABC123456789.' and 'To authorize the ArcSDE component of ArcGIS Server, provide your ArcGIS Server authorization number.' A text input field is present, with the label 'ArcGIS Server' positioned to its left. This input field is circled in red. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'.

12. If you do not receive a congratulations message as it may be an internet interruption. If you are not successful, contact your ESRI representative for an authorization file. Click Finish.




Install SQL Server Native Client

You will need to install the exact version of SQL Server Native Client on each workstation that will connect using ArcMap or ArcCatalog to the Geodatabase.

- When using SQL Server 2012 with ArcSDE v10.2, each client (ArcGIS for Desktop, Server) needs the SQL Server Native Client 64 bit 2008 R2 or 2012. Latest SQL Server 2012 Native 64 bit Client download link: <http://www.microsoft.com/en-us/download/details.aspx?id=29065>


Connect and Create Geodatabase in Workgroup

1. Open ArcCatalog or ArcMap -> Embedded ArcCatalog and expand the database server's item in the TOC. Click on Add Database Server.




Notes: _____


2. After the connection has been established, you have the choice of creating a Geodatabase by right clicking on the instance and choosing new Geodatabase.




3. Create new Geodatabase and change the location if needed of the database file. Also, you have the option of changing the initial size but the autogrow method will be established. Click OK.




- Once complete you will see a new database in your instance. Afterwards, you can add users to the instance by right clicking on the instance in the TOC and choosing permissions.




- This is where you can add users and groups within your organization from Active Directory.




6. Once you click ok, you then need to make a decision if they are going to be server administrators or not. In this example, they are not server administrators. Click ok or apply.




7. Next, you need to assign the group or user per Geodatabase if you have more than one. Because I separate Raster and Vector Geodatabases, the permissions change for users and groups depending on the intent for use. Right click on the new Geodatabase and select administration permissions in the drop down menu.




8. In the permissions: <database> dialog, select the group or user you would like to add permissions to and select the appropriate permission. In this example, I will be giving the GBAMSSales group read/write permissions. Click ok or apply. Notice the other options available for Workgroup for example, backup, Administer Geodatabase, detach, save connection, compress, Geodatabase maintenance, and change versions. We will explore these tasks in subsequent sections.



9. For your users who edit and publish maps, you will want them to create a connection to the database. You can add database connections using the database connection utility as well. This is a primary connection for anyone running full versions of SQL Server. Go to the TOC of ArcCatalog again and expand Database Connections.



10. Click on 'Add Database Connection'. Add instance and the database to the connection strings. You have the choice of authenticating using the operating system or SQL Server user accounts. In this example, we are going to use the OSA method. Click ok.



Database Connection

Database Platform: SQL Server

Instance: luksavage\sqlexpress

Authentication Type: Operating system authentication

User name:


Password:

Database: Vector

[About Database Connections](#) OK Cancel

11. The connection string for the name of the connection is always arbitrary. Recommend using the following naming convention.


- <instance if more than one instance; if not skip>.<database>.<version>.<OSA or SQL user>
- For this example, we will be renaming the connection to vector.default.osa.
- Right click on the new connection and select rename. Type in the new name.

 vector.default.osa


Notes: _____

Registering the Geodatabase in ArcGIS for Server


1. If you are using Operating System Authentication to publish map services and in order for ArcGIS for Server to connect to your database, you need to add ArcGIS for Server service user as read or read/write depending on your uses. Otherwise, use a SQL Server user so you don't need to add ArcGIS for Server service user in the database.
2. You can either grant permissions to ArcGIS for Server service user through the Geodatabase Administration toolset in ArcCatalog or you can add the user in SQL Server and then grant permissions of the data to the user. In this exercise, we'll go through and add ArcGIS for Server user to SQL Server. This exercise is beneficial for GIS workflow scenarios. We will be assigning ArcGIS for Server service user that has read/write access to the database with no DBO or other special privileges.
3. Go to SQL Server Management Studio and add the new user to your Geodatabase or Geodatabases. Open Security within the SSMS TOC and right click on logins. Select new login. Add ArcGIS for Server Service user to the Geodatabase. Recommend assign a default database to general groups or users to be other than master.
4. Go to User Mapping and select on the appropriate databases you want ArcGIS for Server service user to connect to. Make sure it has db_datareader or db_datawriter enabled depending on the functionality you want. You may still need to assign privileges within ArcCatalog in an enterprise setup.




5. Click ok and go to your workstation and open ArcCatalog. Go to the GIS Servers section within the TOC of ArcCatalog. Connect to the administration connection by double clicking the connection or right click and choose connect.




6. Once connected, right click on the connection and choose server properties.




7. Go to the data store tab and click the plus button.



8. Notice I already have LucityGIS and Raster inside of my data store and now I want to connect to the Replica. Add the replica name and click add for publisher database connection.



9. Add the appropriate information in instance and database. Click ok and ok.




The 'Database Connection' dialog box is shown with the following settings:

- Database Platform: SQL Server
- Instance: test-db
- Authentication Type: Operating system authentication
- User name: (empty)
- Password: (empty)
- Database: Replica

At the bottom, there is a link [About Database Connections](#) and buttons for OK and Cancel.

10. Your database should have a green check next to it to signify completed successfully.



The 'ArcGIS Server Properties' dialog box is shown with the 'Data Store' tab selected. The 'Registered Databases' list contains:


- LucityGIS
- Raster
- ✓ Replica

The 'Registered Folders' list is empty. To the right of the lists are buttons for adding (+), removing (x), and refreshing (circular arrow) items. At the bottom, there is a link [About registering databases and folders](#), a 'Validate All' button, and buttons for OK, Cancel, and Apply.

11. Now you are ready to publish map services from connections to the SQL Server Enterprise Geodatabase.


Create Enterprise Geodatabase (formerly ArcSDE)

1. Choose the database platform you will be connecting to. Since ArcGIS is SQL Server friendly, this will demonstrate the sql server platform type.
2. Within SQL Server, an instance is the container or the repository of the databases.
3. Database would be a name given to the database. In SQL Server's case, you will be specifying a name of the database. In this example, we will be creating a database called "vector".
4. Since I have mixed mode turned on for sql authentication, I chose to use the sa account. As the sysadmin, I could have created a database using my OSA account; however, for organizations that have changes, I would recommend creating the database using the SA as this will tag the database to be owned by sa. For most cases, a mixed mode sql instance is the best practice. This gives your organization the flexibility of using both the sa account and OSA when managing databases. **If a DBA is let go and they have created databases using their credentials and the SQL Server instance is set to only use OSA credentials, you will not like the outcome.**
5. Uncheck sde owned schema as this was the old way ESRI used to use for the ArcSDE setup and configuration. DBO schemas are much preferred as they have the most flexibility of use within a windows environment.
6. Authorization file is the file created after authenticating ArcGIS for Server (i.e. c:\program files\ESRI\ License10.3\sysgen\keycodes)




Publishing and Configuring Map Services


1. Open ArcMap and locate your .mxd to publish to ArcGIS Server
 - Recommend: If you have an image, recommend separating the image from the vector map services for performance reasons.
 - Recommend: Cached Image Service
 - Recommend: Converting dynamic labels to Annotation and scale.
 - Recommend: Make your map services scale dependent so not everything shows up in a small scale extent.
 - Recommend: Use ArcGIS Server Web Adapter if using a DMZ. Please consult your IT Administrator for setting up a DMZ.
2. When cartographic and scaling operations are complete, go to the file menu and click on 'Share As/Service'.




3. Share as Service dialog prompts. There are three choices. Choose Publish a service and click next.



4. Publish a Service dialog appears and give it a name. Click Next.



- Service Editor dialog will appear and this is where you add your settings for your map service.



- Click on Analyze at the top of the dialog. After the analyze tool has completed, it will list errors, warnings and messages letting you know if there are any issues with the performance of the data being rendered to ArcGIS Server.

Prepare						
0 Errors		61 Warnings		4 Messages		Search:
Severity	Status	Code	Description	Name	Type	Data Frame
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Street Light	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Facility Building	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Park Path	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Park Landscape	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Parks	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Street Median	Layer	Layers
Medium	Resolved In Map Service Definition	10009	Enabling the option to convert layer transparency to colo...	Parcels	Layer	Layers
Medium	Unresolved	10016	Layer uses symbol level drawing with a transparent color	Park Path	Layer	Layers
Medium	Unresolved	10016	Layer uses symbol level drawing with a transparent color	Park Landscape	Layer	Layers
Medium	Unresolved	10017	Layer uses symbol level drawing with a picture marker sy...	Street Sign	Layer	Layers
Medium	Unresolved	10017	Layer uses symbol level drawing with a picture marker sy...	Street Sign	Layer	Layers
Medium	Unresolved	10017	Layer uses symbol level drawing with a picture marker sy...	Street Sign	Layer	Layers
Medium	Unresolved	10017	Layer uses symbol level drawing with a picture marker sy...	Street Sign	Layer	Layers
Medium	Unresolved	10017	Layer uses symbol level drawing with a picture marker sy...	Street Sign	Layer	Layers

- If errors, you need to resolve before proceeding.
- If warnings, you may or may not address these issues but ESRI highly recommends fixing these issues.
- Messages are helpful hints on low priority performance issues. Most of the time, these do not need to be addressed as issues as they are intended.

7. Go to parameters in the TOC for the Service Editor dialog and change the anti-aliasing to Normal. Not all map services will show artifacts but if so normal is a good place to start.

Note: Anti-Aliasing: A graphics technique that blends foreground and background pixels near edges of objects to trick your eye into seeing smoother borders. You can use this option if unwanted artifacts appear in your map displays, for example, jagged lines, wavy lines or bands, and moiré patterns.


Use the following options to get the graphics effect and performance that will meet your map service needs:

- *None: No antialiasing is performed.*
 - *Fastest: Minimal antialiasing is performed, optimized for speed.*
 - *Fast: Some antialiasing is performed, optimized for speed with better quality than can be achieved with Fastest.*
 - ***Normal: A good balance of speed and quality.***
 - *Best: The best quality antialiasing. This option takes the longest to render.*
- Force text anti-aliasing should be enabled by default.
8. Change the maximum number of records returned by the server. This will increase the records returned by one query. 3000 is a good number to return unless your users need more.


The screenshot shows the 'Service Editor' dialog box with the 'Parameters' tab selected. The 'Connection' is 'arcgis on lukesavage_6080 (admin)' and the 'Service Name' is 'sewer'. The 'Document Location' section shows 'Original Document' and 'Published Document' both set to 'C:\arcgisservice\MapServices\sewer.mxd'. The 'Anti-Aliasing' section has 'Anti-Aliasing' set to 'Normal' and 'Text Anti-Aliasing' set to 'Force'. The 'Properties' section shows 'Maximum number of records returned by the server' set to '3000'. The 'Cluster' section shows 'Choose the cluster hosting the service' set to 'default'. The 'Output Directory' section shows 'Directory' set to 'C:\arcgisservice\directories\arcgisoutput'.

Unlock Schema


1. Set SchemaLockingEnabled to False in Service Properties of ArcGIS for Server disables schema locking. For those who wish to serve their production data as a map service, this is extremely helpful if you need to make any kind of schema changes in your database. However, **feature services will persist a schema lock** and override this setting.
2. Within the service editor dialog when publishing a map service, go to Parameters within the menu tabs on the left and click on advanced.




3. Click on the 'Advanced' button and change the values for schemaLockingEnabled to false if you don't want the map service to lock your database. Click ok when finished.




- Go to the Capabilities tab and make sure the Mapping service is the only box checked.



- In pooling, usually 1 minimum and 5 maximum will suffice for most organizations. For large organizations, increase based on user load.
- In Processes, go to recycle this configuration every: <number> and change to a desirable value. Usually, 12 hours is a good recycled time frame.
- Change the starting at value to 6:00 am or whenever you would like it to start



- If you want to cache, click on caching and change the values to a suitable number. For basemaps and imagery, recommend caching. For interactive map services, leave caching turned off which default.
- If you want to see the speed of your map service, click the preview icon in the menu toolbar. Otherwise, click publish.



is by
on
on

10. Below are Lucity map service deployment scenarios.


- You may have multiple map services for each group if needed. It really depends on your setup with replication, versioning and how complex this may be. Each organization may be different on how they want to handle distributing maps to the users.
- Create Basemaps and Imagery services (tiled) for distribution to your users. Consider your users and what content they would like to see in Basemaps.
- Make sure you're basemap services are using the same coordinate systems (prefer wkid) in the publishing map document.
- Make sure operational layers are using wkid for the coordinate system in your map document.

Notes: _____


Enabling the Geometry Service

We need to enable the geometry service for Lucidity GIS Web Map application to allow for buffering, projecting, calculating lengths and areas.


1. Log into ArcGIS Server Manager.



2. Once logged in, go to the site root tab on the left side of the browser and click on the folder called 'Utilities'




3. Go to the Geometry Service and click on the play icon ► to start a stopped service.
4. Once complete, the service is now available.




Creating a Geocoding Service

Geocoding services allow ArcGIS Web Map to find and display addresses on a map and see how they relate to surrounding features. We do support composite geocoding services.

1. Open ArcCatalog
2. Create a geolocator in your publishing database
3. For dual ranges, make sure to set the 'Match with no zones' value to Yes




4. Right click on the geolocator in the Catalog Tree and click on Share As/Geocode service



5. Publish a service
6. Click Next


7. Make the service name simple so it's easier to remember.



The 'Publish a Service' dialog box is shown. It has a title bar with a close button. The main area contains the following fields and controls:

- Choose a connection:** A dropdown menu showing 'arcgis on lukesavage_6080 (admin)' with a small icon to its right.
- Server type:** A label followed by the text 'ArcGIS Server'.
- Service name:** A text input field containing 'GeoLocate'.
- Navigation buttons:** At the bottom, there are three buttons: '< Back', 'Next >' (highlighted with a blue border), and 'Cancel'.

8. Click Next
9. Choose a folder or keep default location as root
10. Click Continue
11. Select Parameters and change the interactive Find if you want more than 500 records returned by the server.



The 'Service Editor' dialog box is shown. It has a title bar with a close button. The main area is divided into two panes:

- Left Pane (Navigation):** A list of tabs: 'General', 'Parameters' (selected and highlighted in blue), 'Capabilities', 'Pooling', 'Processes', and 'Item Description'.
- Right Pane (Parameters):** Contains the following settings:
 - Cluster:** A label followed by a dropdown menu showing 'default'.
 - Interactive Find:** A label followed by a text input field containing '1000'.
 - Batch Geocoding:** A label followed by two text input fields, both containing '1000'.


At the top of the right pane, there is a status bar with the text 'Connection: arcgis on lukesavage_6080 (admin) Service Name: GeoLocate' and two icons: a green checkmark labeled 'Analyze' and a blue document icon labeled 'Publish'.

12. Analyze and fix any errors. If no errors, publish


Securing a Map Service

Starting at Lucity 7.60, we are supporting ArcGIS for Server secure map services. In this section, we will describe the deployment of secure map services as a built-in user store.


1. Log into ArcGIS Server Manager.



2. Go to the Security menu to configure the security features.
3. Click on configuration settings pencil to configure the type of data store.




- Again, we will be configuring a built-in store at the ArcGIS for Server level not the web store or the windows domain/LDAP configuration in this example.



The 'Security Configuration Wizard' dialog box is shown. It has a title bar with the text 'Security Configuration Wizard' and a close button. The main content area is titled 'User and Role Management' with a 'Help' link. Below the title, it says 'Choose the source of users and roles you will use for ArcGIS Server security.' and 'Choose one of the following options:'. There are three radio button options: 'Users and roles from ArcGIS Server's built-in store' (which is selected and has a red arrow pointing to it), 'Users and roles from an existing enterprise system (LDAP or Windows Domain)', and 'Users from an existing enterprise system (LDAP or Windows Domain) and roles from ArcGIS Server's built-in store'. At the bottom right, there are 'Next' and 'Cancel' buttons.


- Click Next
- Finish after reviewing configuration
- Optional (if using tokens), configure your Long-Lived tokens to the appropriate IT policy. In this example, the lifespan for Long-lived tokens will be 1 day.



The 'Edit Token Settings' dialog box is shown. It has a title bar with the text 'Edit Token Settings' and a close button. The main content area is titled 'Edit the token settings and click Save' with a 'Help' link. Below the title, there are two spin box controls: 'Lifespan of Short-lived Tokens: 60 minutes' and 'Lifespan of Long-lived Tokens: 1 days' (with a red arrow pointing to the '1' in the spin box). Below these is a text box for 'Shared key:' containing the value 'b53f7567-30c3-415d-939f-7'. A note below the text box states: 'The shared key, used to encrypt and decrypt tokens, is critical to ensuring the identity and authorization of clients. The key should be set using 16 random characters.' At the bottom right, there are 'Save' and 'Cancel' buttons.


- Click Save

9. Go to the roles submenu of security



10. Click new role


11. Add a role called 'viewer'. In this example, we will create a role used for the end user. You can similarly create roles for administrators and publishers in the same way. If you already had a user create, you can add them to the role by clicking the person with the plus sign icon



12. Once finished, click on create.

13. In this example, we will create a user. Go to the submenu item called 'users'.


14. Click on new user.



15. Once the 'new user' dialog appears, add the user information. In this example, we will be adding the newly create role to the user during the creation of the user account.


16. Add the information in the 'new user' dialog

17. Click on the person with the plus sign icon



18. Click create


19. We now have the new user added to the users list.




20. Assuming you published a map service for the intention to secure, go to the main menu and click on 'services'




21. Click on the lock icon
22. Click on the radio button 'Private, available only to selected users' to enable security. You have the choice to allow access to all users who are logged in which gives access to all users in the 'built-in' users security store but in this example we only want to use the 'viewers' role.
23. A message will appear 'no roles have been selected'. This is a friendly reminder that there have been no roles selected.



24. Click on the person with the plus sign icon  under roles. This will add the 'viewers' role into the 'Allowed roles' dialog.



25. Click Save


26. For the map service, you should now see the lock icon  in the locked position.



27. Test the map service security. You can do this by going to the rest endpoint of the map service.

28. Example: <http://<servername>/<alias>/rest/services/<nameofmapservice>/MapServer>

29. Supply the newly created user credentials and click on login



30. If you see the rest service directory open, you have successfully secured your service.



map

How to Create a Feature Service

Added GIS Functionality


- In Lucy 7.60, we created a new redlining tool in Lucy WebMap.
- In Lucy 2014 R2, we enabled feature services to replace the Lucy Server Object Extension (SOE) and extend the capability to sync from GIS to Lucy (Webmap and Mobile) and vice versa.

Note: SOE will continue to be supported in this version.


Redlining

To configure the Geodatabase and ArcGIS for Server to enable redlining capability, we must create a feature class or feature classes depending on the type of redlining capability you desire. We support points, lines and polygons. Below we will demonstrate the creation of a feature dataset, three feature classes and published them to a feature service.

1. Open ArcMap
2. Click on the Catalog button if it is not already open.




3. In the Catalog Tree, go to database connections and open your production GIS database.




4. Right click on the connection and choose new and a submenu will appear.

5. Click on Feature Dataset




6. Give the Feature Dataset a name. In this example we will call it Redlining



7. Click Next

8. Set your coordinate system for the feature dataset




9. Click Next

10. Click Next unless you need vertical coordinate systems applied to the data


Notes: _____

11. Set your Z, M and XY tolerance. In this example, we will take the defaults.



12. Click Finish

13. In the Database Connection, right click on the newly created Feature Dataset and choose new and submenu Feature Class



14. In this example we will create a point Feature Class and call in RPoint

The screenshot shows the 'New Feature Class' dialog box. The 'Name' field contains 'RPoint' and the 'Alias' field contains 'Redlining Point'. Under the 'Type' section, the dropdown menu is set to 'Point Features'. In the 'Geometry Properties' section, there are two unchecked checkboxes: 'Coordinates include M values. Used to store route data.' and 'Coordinates include Z values. Used to store 3D data.'. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted with a blue border.

15. Click Next

16. Except defaults unless you are using configuration keywords

17. Click Next

Notes: _____

18. Add desired fields to your redlining point feature class. If you plan on using editing user, date and last editing fields, make sure you turn on editor tracking after creating the feature class.

New Feature Class

Field Name	Data Type
OBJECTID	Object ID
SHAPE	Geometry
NAME	Text
DESCRIPTION	Text
NOTES	Text
NOTES2	Text
GlobalID	Global ID
created_user	Text
created_date	Date
last_edited_user	Text
last_edited_date	Date

Click any field to see its properties.

Field Properties

Alias: OBJECTID


Import...

To add a new field, type the name into an empty row in the Field Name column, click in the Data Type column to choose the data type, then edit the Field Properties.

< Back Finish Cancel

19. Click Finish
20. Repeat steps 13 through 18 to create polygon and line Feature Classes if desired.
21. Make sure to assign credentials for access to the newly create feature dataset and optional versioning before publishing.
22. Optional: Right click on each feature class that you would like to enable edit tracking and choose properties.
23. Go to the tab Editor Tracking and click on Enable Editor Tracking
24. Map the fields to the appropriate Feature Class fields

25. We only use UTC



The image shows the 'Feature Class Properties' dialog box with the 'Editor Tracking' tab selected. The 'Enable editor tracking' checkbox is checked. Under 'Update these fields when a feature is created', the 'Creator Field' is set to 'created_user' and the 'Create Date Field' is set to 'created_date'. Under 'Update these fields when a feature is edited', the 'Editor Field' is set to 'last_edited_user' and the 'Edit Date Field' is set to 'last_edited_date'. The 'Record Dates in:' section has 'UTC' selected with a radio button, and 'Database Time' is unselected. A note below states: 'Pre-existing dates in create date and edit date fields will be considered to be in the specified time zone. UTC is recommended if there are no dates. See the on-line help for more information.' At the bottom are 'OK', 'Cancel', and 'Apply' buttons.

Feature Class Properties

Fields Indexes Subtypes Feature Extent Relationships Representations

General Editor Tracking XY Coordinate System Domain, Resolution and Tolerance

☒ Enable editor tracking

Update these fields when a feature is created

Creator Field: created_user

Create Date Field: created_date

Update these fields when a feature is edited

Editor Field: last_edited_user

Edit Date Field: last_edited_date

Record Dates in: ☒ UTC ☐ Database Time

Pre-existing dates in create date and edit date fields will be considered to be in the specified time zone. UTC is recommended if there are no dates. See the on-line help for more information.


OK Cancel Apply

26. Click Apply or ok.


Notes: _____

Publishing a Feature Service

1. Go to the File/Share As/Service menu option to create a service




2. Select Publish a Service



3. Click Next

4. Choose server connection and create service name




The 'Publish a Service' dialog box is shown. It has a title bar with a close button. Inside, there is a section 'Choose a connection' with a dropdown menu showing 'arcgis on lukesavage_6080 (admin)' and a plus icon. Below this, 'Server type:' is set to 'ArcGIS Server'. The 'Service name' section has a text box containing 'redlining'. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

5. Click Next

6. Use in folder or in the root of ArcGIS service directory

7. Click Continue


8. Go to Parameters and click on Advanced



The 'Service Editor' dialog box is shown. It has a title bar with a close button. Below the title bar, there is a status bar showing 'Connection: arcgis on lukesavage_6080 (admin)' and 'Service Name: redlining'. To the right of the status bar are icons for 'Import', 'Analyze', 'Preview', and 'Publish'. On the left, there is a sidebar with a list of tabs: 'General', 'Parameters' (selected), 'Capabilities', 'Mapping', 'KML', 'Pooling', 'Processes', 'Caching', 'Item Description', and 'Sharing'. The main area is titled 'Parameters' and contains several sections: 'Document Location' with 'Original Document' set to 'C:\Demo\redlining.mxd' and 'Published Document' set to 'The service has not yet been published'; 'Anti-Aliasing' with 'Anti-Aliasing' set to 'None' and 'Text Anti-Aliasing' set to 'Force'; 'Properties' with 'Maximum number of records returned by the server' set to '1000' and an 'Advanced...' button; 'Cluster' with 'Choose the cluster hosting the service' set to 'default'; and 'Output Directory' with 'Directory' set to 'C:\arcgisserver\directories\arcgisoutput'.


9. Click Ok

10. Go to the Capabilities tab and make sure Mapping and Feature Access is selected.



Notes: _____

11. Click on the submenu tab 'Feature Access' and add the selection 'Enable ownership-based access control on features'. This option will only allow the created user features to be updated by the owner of the features but only allow the other users to query the created data.



12. Analyze to make sure no errors are present.
13. Click Publish
14. Optional: If you wish to secure the feature service, go to the below section of 'Security a Map Service' and add each user account to have access to the newly created map/feature service.
15. For Editing feature services, go through the same process above. Make sure you are using an edit user when publishing.

Notes: _____

Publishing an Offline Feature Service

In order to support offline mode, we must prepare the data and configure the feature service. Below, we will demonstrate the setup for supporting offline feature services.

Prepare Data

- Add GlobalIDs
- Enable geodatabase archiving
 - Make sure there is enough space for your database to grow before enabling archiving on your enterprise geodatabase
- You have the capability to add create, delete, query, sync and update.
 - For Lucy, we currently do not plan to provide offline map edits.


Publishing Preparation

- Consider symbology
- Feature Services will lock database for any schema changes.
- Needs to be an edit user to database when publishing map
- Consider securing feature service
- Remove Joins
 - Joins and Relates are not accessible through Feature Services
- Ensure all layers are in the same versioned/un-versioned state
 - Layers in the TOC cannot have mix match of versioned and un-versioned data

Notes: _____

End Users

- Make sure you are connected to a fast internet connection or LAN line when checking out map data
1. Open ArcCatalog. Right click on your feature classes or feature datasets and choose manage, Add GlobalIDs.



2. To enable archiving, right Click on Feature Datasets or Feature Classes You can either publish a new map/feature service or enable the feature service within an existing map service. In order to have sync capability, make sure you log in as an edit user.

4. Like with Redlining, go through the process of publishing a feature service but adding sync capability. You can have create, delete, query, sync and update enabled.

Service Editor

Connection: arcgis on test-web_6443 (admin) Service Name: demo_secure

General
Parameters
Capabilities
Mapping
Feature Access
Pooling
Processes
Caching
Item Description

Feature Access

REST URL:

SOAP URL:

Operations allowed:

☒ Create ☒ Delete ☒ Query ☒ Sync ☒ Update

Properties

☒ Allow geometry updates
☐ Allow update of true curves

☒ Apply default z-value
When inserting or updating features with no z-values, set z-value to:

☐ Enable ownership-based access control on features
Operations allowed on features created by other users :
☒ Query ☐ Update ☐ Delete

Advanced Options...

OK Cancel

Notes: _____
